

I2b2 Install: Full VM Server Installation Guide

TABLE OF CONTENTS

Contents

1	INSTALL.....	1
1.1	Installing the Software.....	1
1.2	Installing the i2b2 VMware image application.....	1
2	EXECUTE.....	1
2.1	Running the VMware Server Console- Windows.....	1
2.2	Running the VMware Server Console- Mac.....	1
3	CONFIGURE.....	1
3.1	Configure the web browser.....	1
4	LICENSES.....	1

1 INSTALL

1.1 Installing the Software

1. Download VMware Player(windows) or VMware Fusion (Mac) from [Home - Support Portal - Broadcom support portal](#)
2. Install the download into a directory of your choice


1.2 Installing the i2b2 VMware image application

1. The complete VMware i2b2 server image pre-installed in Rocky Linux environment is available for download on <https://www.i2b2.org/software/index.html>
2. Click on **i2b2VMware** zip file under Download to download it your local machine
3. Extract all the files from the downloaded zip file into C:\Virtual Machines\.
4. A folder called **i2b2 Server** will be created automatically when the files are extracted from the zip file to the Virtual Machine directory

2 EXECUTE


2.1 Running the VMware Server Console- Windows

1. Go to the downloaded VMWare software location
2. Run the VMware Workstation Player




3. Click on the Open Virtual Machine icon

- 4. Navigate to the extracted VM directory and select the i2b2 Server virtual disk file
- 5. **i2b2 Server** will be added to the list and select it and click Play Virtual Machine




2.2 Running the VMware Server Console- Mac

- 1. Run the VMware Fusion.
- 2. Click on install or image icon
- 3. Navigate to the extracted VM directory and select the i2b2 Server virtual disk file




- 4. Click on Run arrow image




3 CONFIGURE

3.1 Configure the web browser


- 1. Once you start the Virtual Machine the following will appear in the terminal window



- 2. Double click on the **i2b2** Server
- 3. Click on **Show Apps** icon



- 4. Click on **Firefox** browser icon
- 5. I2b2 Web client is displayed. Default url: `http://localhost`.
- 6. Login with user: demo ; password: demouser



4 LICENSES

The i2b2 source code is licensed under Mozilla Public License 2.0.